



**DIGITAL AND
POPULATION DATA
SERVICES AGENCY**

Atostek ID 4.4 User Guide

for Windows

v1.0

Atostek

Table of Contents

1. ATOSTEK ID SOFTWARE DESCRIPTION	4
2. BEFORE USE AND HOW TO START USING ATOSTEK ID	5
2.1. What is Atostek ID?	5
2.2. What do I need to use Atostek ID?	5
2.2.1. Installing Atostek ID	5
2.3. Activating the smart card	7
3. DIGITAL AUTHENTICATION AND DIGITAL SIGNATURE	9
3.1. Digital authentication	9
3.1.1. mTLS authentication	10
3.1.2. Authentication via the SCS interface	10
3.1.3. Using Atostek ERA	10
3.2. Digital signature	11
3.2.1. Signing of PDF documents (Adobe Acrobat, PDF-XChange)	12
3.2.2. Signing via the SCS interface	12
3.2.3. Signing in the Atostek ERA system	12
4. FEATURES	14
4.1. Starting and shutting down	14
4.2. Application information and user guide	14
4.3. Changing PIN codes and unlocking locked codes	14
4.4. Readers and cards	15
4.5. Settings	16
4.5.1. Language	17
4.5.2. Notify when updates are available	17
4.5.3. Notify when only partial connection to browser is available	18
4.5.4. Show "Log in to ERA" in pop-up menu	18
4.5.5. Start Atostek ID on boot	18
4.5.6. Enable MIFARE Chip Read and Write Features	18
4.5.7. Allow logging	18
4.5.8. Turn on debug logging	18
4.5.9. Seconds to wait for reader and card to be inserted	18
4.5.10. Automatic login retries (0-5)	18

4.5.11.	Register erasmartcard:// -protocol	19
4.5.12.	Register erasmartcardpost:// -protocol	19
4.5.13.	Timestamp server address	19
4.5.14.	Custom login command	19
4.5.15.	Custom launch commands	19
4.5.16.	Set SCS certificate as trusted in Firefox	20
4.5.17.	Open SCS server certificate download page	20
4.5.18.	Settings file parameter CLEANCERTSTOREONCARDREMOVAL	20
4.5.19.	Settings file parameter EXCLUDEDREADERS	20
4.5.20.	Settings file parameter EXCLUDEDCARDTYPES	21
4.5.21.	Settings file parameter ERRORLOGPATH	21
4.5.22.	Settings file parameter MULTIDESKTOPMODE	21
4.5.23.	Settings file parameter ALLOWEDBROWSERLESSANDFORWARDDOMAINS	21
4.6.	Updating	22
4.7.	Signing documents via the application	22
4.8.	Email encryption and signing (Outlook)	23
4.9.	Workstation login	23
4.10.	MIFARE Chip Management	24
4.11.	Logging	26
4.12.	Error reporting	26
4.13.	Diagnostics	27
5.	FREQUENTLY ASKED QUESTIONS AND ERROR SITUATIONS	30
5.1.	Frequently asked questions	30
5.2.	Other problem situations	31
5.2.1.	Atostek ID and Minidriver	31

1. Atostek ID software description

Atostek Oy is a Finnish software company founded in 1999, specializing in healthcare and medical applications, industrial product development, and IT consulting for the public sector. Atostek's products include the Atostek ID card reader software and the Atostek ERA system.

Atostek ID will be offered as the official card reader software by the Digital and Population Data Services Agency starting in 2024. The software is intended for use with the certificate cards issued by the Digital and Population Data Services Agency. Using the software with cards, various operations such as digital authentication and digital signatures can be performed via multiple interfaces and modules. Additionally, the software supports certificate card activation, PIN handling, and viewing card information. Alongside the Atostek ID application, the software includes the Atostek ID Minidriver, Atostek ID TokenDriver, Atostek ID PKCS#11 modules, and the Atostek ID AD registration service. Furthermore, Atostek ID supports the issuance of backup cards by the Digital and Population Data Services Agency. In addition to the aforementioned functions, Atostek ID offers compatibility with the Atostek ERA system via the erasmartcard.ohoito.fi interface. Atostek ID was previously known as ERA SmartCard.

Installation packages and documentation for the Atostek ID software can be downloaded from both the website of the Digital and Population Data Services Agency and Atostek's own driver download page. The Digital and Population Data Services Agency will generally announce software updates. Atostek will inform its contractual customers about updates according to specific agreements. In the event of errors or issues, individuals and organizations that have obtained software access through the Digital and Population Data Services Agency should primarily contact the support of the Digital and Population Data Services Agency (1st line support), which will forward requests to Atostek if necessary (2nd line support). Atostek's contractual customers should contact Atostek support directly in case of errors or issues, according to the terms of their agreement. The Digital and Population Data Services Agency and Atostek will inform about specific issues related to the software if necessary.

The Atostek ID software and its user guides have undergone accessibility evaluations in accordance with the WCAG 2.1 and 2.2 standards. The accessibility statement can be found on the website of the Digital and Population Data Services Agency alongside the driver downloads. The software undergoes security audits at regular intervals as agreed between Atostek and the Digital and Population Data Services Agency. The audit report will be made available on the website of the Digital and Population Data Services Agency alongside the driver downloads after the audit. Atostek ID is also part of the annual audit of the ERA system. The development of Atostek ID software is also guided by Atostek's ISO 9001 certified quality system.

The functionality of the Atostek ID card reader software is not guaranteed if other similar card reader software is installed on the workstation. For inquiries related to further development and additional features of the software, please contact Atostek directly (for Atostek's contractual customers) or the Digital and Population Data Services Agency.

2. Before use and how to start using Atostek ID

This chapter introduces the Atostek ID application. In addition, the requirements for using the application are explained and instructions are given on how to install the Atostek ID application on a Windows computer. The Atostek ID application supports all versions of the Windows operating system (Windows and Windows Server) maintained by Microsoft.

2.1. What is Atostek ID?

Atostek ID is card reader software used with certificate cards issued by the Digital and Population Data Services Agency. These cards include professional, personnel and operator cards for social welfare and healthcare, organization cards, related backup cards, and citizen certificate cards (identity cards). The cards can be used for digital authentication and digital signatures in services and applications compatible with the software. In addition, the software supports certificate card activation, PIN handling, and viewing card information.

2.2. What do I need to use Atostek ID?

Atostek ID is compatible with the Windows and Windows Server operating systems. Check the latest list of supported Windows versions from the website of Digital and Population Data Services Agency <https://dvv.fi/en/card-reader-software> or from the page <https://downloads.ehoito.fi> before installation.

Note! If you are using a macOS or Linux (Debian, Red Hat) operating system, see the user guide for that operating system.

Note! Separate installation instructions are available for the software, detailing each step of the installation process.

Note! A separate integration guide is also available for the software, intended specifically for system developers and the IT departments of organizations.

To use a certificate card with Atostek ID software, you will need a card reader and a card reader driver in addition to the program. The card reader driver is usually already included in the operating system. If the driver is not found or requires an update, you can download the necessary installation packages directly from the card reader manufacturer's website. Atostek ID supports card readers compliant with the PC/SC specifications.

Atostek ID supports web browsers Microsoft Edge, Mozilla Firefox, Apple Safari, and Google Chrome, specifically the versions currently supported by the browser vendors. Older versions of these browsers are not systematically tested. Atostek ID supports email applications Outlook, Apple Mail, and Thunderbird for encryption and signing. The software also supports Adobe Acrobat and PDF-XChange for signing PDF documents. Atostek ID is available in Finnish, Swedish, and English.

2.2.1. Installing Atostek ID

To install Atostek ID, follow the instructions below:

1. Go to the page <https://dvv.fi/en/card-reader-software> or <https://downloads.ehoito.fi>.
2. Select the driver for the correct operating system and download it.
3. Follow the installation instructions. If necessary, consult the Atostek ID installation guide.




Figure 1. Atostek ID application.

After installation, the Atostek ID application can be found in the Windows taskbar. To view the application menu, open the taskbar notification area from the arrow and right-click the Atostek ID icon (Figure 1). The program's logo is red if no card readers are connected. The logo is yellow if no cards are connected. The logo is green if a card is connected and its information has been successfully read. The logo also indicates situations where reading the card information is in progress or the program is in an erroneous state.


If you receive error messages from the Atostek ID application immediately after installation, please check that you do not have another smart card reader software installed at the same time. The earlier card reader software from the Digital and Population Data Services Agency may interfere with the operation of the Atostek ID software if both are used simultaneously.

The application is then fully ready for use.

2.3. Activating the smart card

Activate the smart card according to the following instructions:

1. Connect the card reader to the computer and insert the smart card into the reader.
2. If the card has not been activated before, the application will show the activation window automatically. The card only needs to be activated once. If the activation window is not shown, select *"Activate card"* from the application menu.
3. In the window that opens (Figure 2), enter the activation code number (PUK) stated in the code letter delivered with the card.
4. Set the PIN for the authentication certificate (PIN1) and the PIN for the signing certificate (PIN2). The window will specify the maximum and minimum lengths of the PINs. After this, you may click *OK*. The success or failure of the activation will be indicated in a separate window.



The screenshot shows a Windows-style dialog box titled "Atostek ID" with a close button (X) in the top right corner. The dialog has a light gray background and a blue border. It contains the following fields and labels:

- Activate card** (Section header)
- Activation PIN (PUK):** A text input field.
- New PIN1 (length 4–8):** A text input field.
- Verify new PIN1:** A text input field.
- New PIN2 (length 4–8):** A text input field.
- Verify new PIN2:** A text input field.

At the bottom of the dialog are two buttons: **OK** and **Cancel**. Below the buttons is the logo of the Digital and Population Data Services Agency, which consists of a stylized blue and green geometric shape followed by the text **DIGITAL AND POPULATION DATA SERVICES AGENCY**.

Figure 2. Activating the smart card

Note that both the PIN1 and PIN2 must be set to activate the smart card. The minimum and maximum lengths of the card's PINs vary depending on the card type and card generation, so the required lengths may differ for your various cards. You need to activate the smart card only once. If you have activated the smart card on another device, you do not need to activate the card again.



Note also that the smart card cannot be activated using an NFC reader, since to establish a secure NFC connection between the card and the reader, the PIN1 code of the smart card must be entered.

Note! Entering the activation code number incorrectly five times in a row will lock the activation code number. After this, the card can no longer be activated or locked PIN codes unlocked. Previously set PIN codes and their associated signatures will still work, even if the activation code number is later locked. The activation PIN cannot be unlocked; obtaining a functioning activation code number requires ordering a new card. The program shows a warning each time the activation PIN is entered incorrectly and displays the number of remaining attempts before the PIN is locked.

3. Digital authentication and digital signature

This chapter describes how you can use the Atostek ID application to perform authentication to a compatible service using your smart card. In addition, this chapter explains how to create a digital signature using the Atostek ID application. Please also refer to the user instructions for the service or application you are using for authentication or performing a signature, if necessary.

This chapter provides a more detailed description of some of the most common use cases related to authentication and signing. Not all possible services are described in this guide, and not all the use cases described here apply to all users. This chapter focuses solely on the functionality of authentication and signing. The next chapter will provide a more detailed overview of the software's other functionalities.

3.1. Digital authentication

The Atostek ID application can be used to authenticate the user when logging into a compatible service. To authenticate the user, the PIN1 code of the smart card must be entered.

To perform the authentication, insert the smart card into the reader, check that the Atostek ID application is running (Figure 1) and start logging into the compatible service. The service provider provides more detailed instructions for logging in. The service calls the Atostek ID application, after which Atostek ID requests the PIN1 code from the user (Figure 3). When prompted for the PIN, you may also see the standard Windows PIN window (without the Atostek and Digital and Population Data Services Agency logos). The PIN windows differ slightly depending on which interface is used for the authentication. If the certificate card is about to expire within two months, Atostek ID will inform you of this during authentication.




Figure 3. Authenticating the user using PIN1 code. During authentication, the standard Windows PIN window may also be shown.

3.1.1. mTLS authentication

Authentication can be performed using the card's authentication certificate via mTLS (mutual TLS) in the browser. In this case, the Atostek ID Minidriver module is utilized, which automatically installs with the Atostek ID Windows version installation. More details about the Atostek ID Minidriver module can be found in the Atostek ID software integration guide.

This type of authentication is used, for example, in public administration service portals (suomi.fi authentication). To authenticate with the service, connect the card reader to your computer, insert the card into the reader, and begin authentication in the browser. You will be prompted for the card's authentication certificate PIN, or the card's PIN1 code. After this, the authentication will be complete, and you will be directed to the service. In case of issues, first refer to chapter 5 of this guide, where solutions to common problems are described.

3.1.2. Authentication via the SCS interface

Authentication can also be performed, for example, by utilizing the SCS interface (Signature Creation Service) of the Atostek ID application. SCS is an HTTPS interface defined by the Digital and Population Data Services Agency, specifically used for web services during authentication. The SCS interface is utilized by, for example, many patient information systems.

The use of the SCS interface is not particularly visible to the user when using the application. To authenticate, you need to connect the card reader to your computer and the card to the reader. After this, you can start the authentication process with the system. At this point, Atostek ID will ask you to select the certificate to be used for authentication. Once the certificate is selected, you will be prompted to enter the corresponding PIN code. After this, the authentication will be complete, and you will be directed to the service.

3.1.3. Using Atostek ERA

Please note that this use case is intended only for social and healthcare users who are registered to use the ERA system. If your organization has not instructed you to use Atostek's ERA system or if you are a citizen user (using an identity card), this use case does not apply to you. In such cases, you can skip this section of the instructions. You are not required to log in to the ERA system unless you have been specifically instructed to do so.

You can log in to Atostek's ERA service using the Atostek ID application. Navigate to the ERA system login page with your browser or select *"Log in to ERA"* from the application menu to open the login page in your default browser. Note that this option is only visible if the option *"Show 'Log in to ERA' in pop-up menu"* is enabled from the settings. This option can also be used to log into ERA when the default ports cannot be opened, because the feature opens the login page with the port information of the Atostek ID application. Such a situation can occur, for example, when several users are logged on to the same computer.

Successful authentication to the ERA system requires that you have been configured in the system beforehand. When authenticating, the card reader must be connected to the computer and the card must be in the reader. Once the authentication process has started, Atostek ID will prompt you for the card's PIN1 code. If authentication is successful, you will be directed to the service.

The ERA system uses the `erasmartcard.ehoito.fi` interface of the Atostek ID application. You can test the functionality of the interface by opening the application menu and selecting *"Diagnostics"*, then *"Open Atostek ID test site"*. This will open the interface test page in your default browser, displaying *"Test page loaded OK."*

3.2. Digital signature

With Atostek ID, the user can use the signing certificate of their certificate card to create a digital signature for a compatible service. During signing, the user must enter the PIN2 of their card.

To create the digital signature, insert the card into the card reader, connect the reader into the computer, and check that the Atostek ID program is running (Figure 1). If necessary, check the instructions of the service or application on how the digital signature is performed in the service or application in question. During signing the service or application calls the Atostek ID application, after which Atostek ID requests the PIN2 code from the user (Figure 4). When prompted for the PIN, you may also see the standard Windows PIN window (without the Atostek and Digital and Population Data Services Agency logos). The PIN windows differ slightly depending on which interface is used for the authentication.




Figure 4. Digital signature with PIN2 code. During signing, the standard Windows PIN window may also be shown.

3.2.1. Signing of PDF documents (Adobe Acrobat, PDF-XChange)

A PDF document can be signed using the Adobe Acrobat and PDF-XChange applications. In this case, the Atostek ID Minidriver module is utilized. The module is automatically installed with the Atostek ID Windows version installation. More details about the Atostek ID Minidriver module can be found in the Atostek ID software integration guide.

When signing with Adobe, select the document to be signed and choose to use the certificate from the tools menu. You can select digital signing from the menu that opens, at which point you will need to draw your signature in the desired location on the document using your mouse. After that, you will be prompted to select the certificate to be used. Once you have selected the certificate, you must enter the PIN code for the certificate in the window that opens. After this, the card will perform the signing, which will be attached to the document.

When signing with the PDF-XChange application, select the document to be signed and then choose 'Sign Document' from the Protect menu in the top bar. Use the mouse to place the signature field in your desired location on the document. Next, select the card certificate you want to use for the signing from the window that opens. You will be prompted for the certificate's PIN code. Once the card has performed the signing, it will be attached to the document.

3.2.2. Signing via the SCS interface

Signing can also be performed, for example, by utilizing the SCS interface (Signature Creation Service) of the Atostek ID application. SCS is an HTTPS interface defined by the Digital and Population Data Services Agency, specifically used in web services during signing. The SCS interface is utilized by, for example, many patient information systems.

The use of the SCS interface is not particularly visible to the user when using the application. For signing, you need to connect the card reader to your computer and the card to the reader. After this, you can start the signing process. At this point, Atostek ID will ask you to select the certificate to be used for signing. Once the certificate is selected, you will be prompted to enter the corresponding PIN code. After this, the signing is complete, and the signature will be passed from the application to the service that requested it.

3.2.3. Signing in the Atostek ERA system

Please note that this use case is intended only for social and healthcare users who are registered to use the ERA system. If your organization has not instructed you to use Atostek's ERA system or if you are a citizen user (using an identity card), this use case does not apply to you. In such cases, you can skip this section of the instructions. You are not required to log in to the ERA system unless you have been specifically instructed to do so.

You can perform a signing operation, such as the signing of a prescription, in Atostek's ERA service using the Atostek ID application once you have authenticated yourself in the system. When signing, the card reader must be connected to the computer and the card must be in the reader. Once the signing process has started, Atostek ID will prompt you for the card's PIN2 code. After this, the card will perform the signature and pass it to the ERA system.



The ERA system uses the erasmartcard.ehoito.fi interface of the Atostek ID application. You can test the functionality of the interface by opening the application menu and selecting *"Diagnostics"*, then *"Open Atostek ID test site"*. This will open the interface test page in your default browser, displaying *"Test page loaded OK."*

4. Features

This chapter introduces the main features of the Atostek ID application. They include, for example, changing and opening access (PIN) codes. In addition, the settings related to the application are presented with instructions on how to change them.

4.1. Starting and shutting down

The Atostek ID application starts automatically after you have installed the application and logged into the operating system. You can turn off automatic starting in the application's settings.

When you wish to close the application, select *"Quit"* from the application menu. This will completely shut down the Atostek ID application. There is usually no need for this, and after this you can no longer log in to the services or create signatures through, for example, the SCS interface or the erasmartcard.oho.fi interface until the program is restarted. The program can be found in the start menu under the name *"Atostek ID"* and can be restarted from there if necessary.

4.2. Application information and user guide

Information about the Atostek ID application, such as the version number and the ports used by HTTPS servers, can be found in the application's About view. This can be accessed by selecting *"About"* from the application's menu. The version number is displayed at the top of the window. Open and closed ports, as well as certificate-related information, pertain to the erasmartcard.oho.fi interface. Additionally, the view indicates whether a connection can be established to port 53952 of the SCS interface. A connection cannot be made if another application is reserving the port. This can occur, for example, if DigiSign card reader software is installed and running on the computer, as it opens its corresponding service on that port. Issues with the SCS interface port will also be indicated in the Atostek ID application's logo as a triangle with an exclamation mark.

The user guide can be accessed through the application by selecting *"Show User's Manual"* from the menu. The user guide opens in the application's language (Finnish, Swedish, or English). Software user guides, installation instructions, and other documentation can also be downloaded from both the Digital and Population Data Services Agency's card reader software page and Atostek's own driver page.

4.3. Changing PIN codes and unlocking locked codes


You can change PIN codes by selecting *"Change PIN1"* or *"Change PIN2"* from the application menu and entering the current PIN code and the new PIN code twice (Figure 5).

You can open locked PIN codes by selecting *"Open PIN1 code with PUK code"* or *"Open PIN2 code with PUK code"* from the application menu and entering the PUK code and the new PIN code twice (Figure 6). The PUK code, also known as the activation code number, is provided with the certificate card.

The card can also be activated through the *"Activate card"* option in the menu. The application prompts the user to activate the card when a non-activated card is inserted into the reader, which means the user does not need to trigger the activation themselves through the menu.

Note! While processing PIN codes, the certificate card must be present in the reader. Both PIN1 and PIN2 codes must be opened for the card to be activated. Activating the card will also open both PINs.

Note! Entering the activation code number incorrectly five times in a row will lock the activation code number. After this, the card can no longer be activated or locked PIN codes unlocked. Previously set PIN codes and their associated signatures will still work, even if the activation code number is later locked. The activation PIN cannot be unlocked; obtaining a functioning activation code number requires ordering a new card. The program shows a warning each time the activation PIN is entered incorrectly and displays the number of remaining attempts before the PIN is locked.



Figures 5 and 6. Changing and unlocking the PIN1 code.

4.4. Readers and cards

Connected card readers and cards can be viewed by selecting “*Readers and Cards*” from the application's menu. In the window that opens (Figure 7), the card readers connected to the computer are listed vertically on the left side. For NFC readers, two different readers will appear in the listing if the reader has both an NFC and a standard USB reader (contact reader) separately. You can select a reader as active by clicking its name in the left-side list of the window.

Once a reader is selected, information about the card connected to the card reader is displayed on the right side of the window, including the name details and expiration date. The window also shows the certificate chain of the card presented in a tree-like structure, from the root certificate through intermediate certificates to the user's certificates. Related to the user's certificates, both the public part of the certificate and the corresponding private key are displayed. The public parts of the certificates can be opened or saved by right-clicking the certificate in the view. This will open an additional menu with the options “*Open*” and “*Save As...*”. Additionally, the validity of certificates can be checked by selecting “*Validity check*”. This checks the certificate's expiration date and revocation lists (CRL, OCSP).




Figure 7. Readers and cards view.

When using the NFC reader, the user is prompted for the card's PIN1 code when the card is brought to the reader. The PIN is used to establish a secure NFC connection. If the card is removed from the NFC reader, the user has 10 seconds to bring the card back before the PIN1 code must be entered again to re-establish the connection.

The Atostek ID Minidriver automatically saves the user's certificates to the Windows certificate store. Atostek ID removes these certificates from the store when the card is removed from the reader.

4.5. Settings

You can edit the application settings by selecting "Settings" from the application menu. With the settings (Figure 8, left) you can, for example, change the application language and modify the settings related to logging. Please note that the changes will only take effect after saving. The settings are detailed in their own subsections. If you work in an organization that uses the Atostek ID application, your organization may manage some or all of the Atostek ID application's settings. In this case, a notice about organizational management will appear in the settings dialog, and the managed settings are disabled and cannot be modified (see Figure 8, right). The user is not able to change these settings on their own. Instead, the organization configures them centrally on the user's behalf via the Windows registry. Settings that are not disabled remain available for the user to modify as usual. Additional instructions for organizations regarding configuration of settings in the registry can be found in the Atostek ID application installation guide (command-line installation with the CONFIGUREREGISTRY parameter).




Figure 8: On the left is the default view of the settings, and on the right is the settings dialog when the organization manages some of the application's settings on behalf of the user.

4.5.1. Language

The "Language" setting allows you to change the language of the Atostek ID application. The languages supported at the moment are Finnish, Swedish, and English.

4.5.2. Notify when updates are available

The "Notify when updates are available" setting can be used to enable Atostek ID notifications of new available versions. When enabled, Atostek ID will send a separate notification that a new version is available for download and installation.

4.5.3. Notify when only partial connection to browser is available

The **"Notify when only partial connection to browser is available"** setting can be used to enable Atostek ID notifications about a partial connection when the application's `erasmartcard.ehoito.fi` interface cannot connect to default ports and the system being used must be opened using Atostek ID launch commands. This setting concerns only the usage of the `erasmartcard.ehoito.fi` interface.

4.5.4. Show "Log in to ERA" in pop-up menu

The **"Show 'Log in to ERA' in pop-up menu"** setting can be used to hide or display the ERA login link in the application menu. Please note that the use of the ERA system applies only to social and healthcare users who are configured to use the ERA system.

4.5.5. Start Atostek ID on boot

The **"Start Atostek ID on boot"** setting can be used to enable or disable the automatic starting of the application. Changing the setting requires admin privileges, which are requested from the user after saving the settings. The application will close while the setting is changed and automatically start up again afterwards.

4.5.6. Enable MIFARE Chip Read and Write Features

The **"Enable MIFARE chip read and write functionality"** setting will display an option *"Mifare"* in the application menu, which opens a separate management view for the MIFARE chip. Please refer to the MIFARE chip reading and writing instructions before attempting any reading or writing. You will need an NFC reader for handling the chip.

4.5.7. Allow logging

With the **"Allow logging"** setting, the logging done by the application can be disabled. Disabling logging does not remove prior logs but prevents the logging of new entries.

4.5.8. Turn on debug logging

The **"Turn on debug logging"** setting allows you to choose whether DEBUG level log messages are logged in the error log or only INFO, WARNING and ERROR level log messages.

4.5.9. Seconds to wait for reader and card to be inserted

The **"Seconds to wait for reader and card to be inserted"** setting allows you to specify the number of seconds during which an unconnected reader or card should be connected after login has started via the `erasmartcard.ehoito.fi` interface. When the value is set to 0, login fails immediately if the reader or card is missing. The maximum value for the setting is 120 seconds. This setting concerns only the usage of the `erasmartcard.ehoito.fi` interface.

4.5.10. Automatic login retries (0-5)

The **"Automatic login retries (0-5)"** setting allows you to define how many times the login is automatically retried if the login fails due to the Alcor Micro reader when the `erasmartcard.ehoito.fi` interface is in use. When the value is set to 0, each retry attempt is asked separately (however, no more than three times in total). This setting concerns only the usage of the `erasmartcard.ehoito.fi` interface.

4.5.11. Register `erasmartcard://` -protocol

The **"Register `erasmartcard://` -protocol"** button allows you to register the `erasmartcard://` -protocol for the Atostek ID application. More information can be found in the installation guide. Changing the setting requires admin privileges, which are requested from the user after saving the settings. The application will close during the change of the setting and then automatically start up again. This setting concerns only the usage of the `erasmartcard.ehoito.fi` interface.

4.5.12. Register `erasmartcardpost://` -protocol

The **"Register `erasmartcard://` -protocol"** button allows you to register the `erasmartcardpost://` -protocol for the Atostek ID application. More information can be found in the installation guide. The application will close during the change of the setting and then automatically start up again. This setting concerns only the usage of the `erasmartcard.ehoito.fi` interface.

4.5.13. Timestamp server address

In the **"Timestamp server address"** field, you can define the timestamp service used to retrieve timestamps for higher-level signatures (e.g., signing a PDF document through the application at PAdES standard levels B-T, B-LT, B-LTA). The timestamp service address is specified wholly, e.g., `https://timestampservice.fi/ts`. Please note that the example timestamp service provided is not a real service. Use your organization's recommended timestamp service.

4.5.14. Custom login command

The **"Custom login command"** field can be used to define a browser that you want to open instead of the default browser when a launch command without a separately defined command is executed. The browser is defined as: `"<Path to browser .exe file> {URL}"`, for example `"C:\Program Files\Google\Chrome\Application\chrome.exe " {URL}"`.

4.5.15. Custom launch commands

The **"Custom launch commands"** section can be used to add new launch links to the Atostek ID menu that can be used to open a system that utilizes Atostek ID and convey the port information of the application. This is especially important in Citrix and RDP environments.

In the launch command attributes, the identifier of the command (Id) is the value with which the launch command can be used, for example, in a command line launch.

In the launch command attributes, the title field is used to define the text that displays in the application menu.

In the launch command attributes, the command field is used to define the browser that you want to open with the command. The format is the same as in the custom login command.

In the launch command attributes, the URL field contains the target URL. The port of Atostek ID can be entered using {PORT} embedding. At launch, Atostek ID replaces the {PORT} text with the actual port where Atostek ID is connected to.

Example of a launch command:

- "Id": edemo
- "Title": Login to edemo service
- "Command": "C:\Program Files\Google\Chrome\Application\chrome.exe" {URL}
- "URL": <https://edemo.atostek.com/>

4.5.16. Set SCS certificate as trusted in Firefox

The **"Set SCS server certificate as trusted in Firefox"** button allows you to add the self-generated CA certificate of the SCS interface as trusted in Firefox. This setting concerns only the usage of the SCS interface.

4.5.17. Open SCS server certificate download page

The **"Open SCS server certificate download page"** button allows you to open the SCS interface page where you can download the CA certificate. The page also contains instructions on how to manually set the certificate as trusted in Firefox. This setting concerns only the usage of the SCS interface.

4.5.18. Settings file parameter CLEANCERTSTOREONCARDREMOVAL

You may use the setting parameter *"CLEANCERTSTOREONCARDREMOVAL"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). The value *"true"* in the setting clears the certificates of the user's card from Windows' certificate store when the card is removed from the reader. The value *"false"*, in turn, preserves the certificates in the store. Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect.

4.5.19. Settings file parameter EXCLUDEDREADERS

You may use the setting parameter *"EXCLUDEDREADERS"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). Give the setting a string-form list of readers (Reader1, Reader2, Reader3) that you want to remove from use. Atostek ID will then ignore the cards in these readers. If the reader name in the "Readers and cards" view ends with extra numbers, exclude them when configuring the setting. For example, if the reader name in the view is "Windows Hello for Business 0", use the string "Windows Hello for Business" in the setting. The setting supports wildcard characters * (matches one or more characters) and ? (matches a single character). For example, the value *ExcludedReaders=ACS** will hide all readers whose name begins with the string "ACS". Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect.

4.5.20. Settings file parameter EXCLUDED CARD TYPES

You may use the setting parameter *"EXCLUDED CARD TYPES"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). Give the setting a string-form list of card types that you want to remove from use. The allowed types are ORGANISATION (organization cards), PROFESSIONAL (professional cards for social welfare and healthcare), PERSONNEL (personnel cards for social welfare and healthcare), IDENTITY (citizen certificates). Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect.

4.5.21. Settings file parameter ERROR LOG PATH

You may use the setting parameter *"ERROR LOG PATH"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). Give the setting the path to which the application's error log should be written, for example *"ErrorLogPath=C:\\Log\\AID.log"*. If the path is erroneous or it does not exist, the application will continue to write the logs to the default location. Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect.

4.5.22. Settings file parameter MULTIDESKTOP MODE

You may use the setting parameter *"MULTIDESKTOP MODE"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). This parameter is used when the organization operates in a Microsoft Azure Virtual Desktop (AVD) environment and has separately agreed to SCS interface support for this multi-user environment. In this case, the organization uses the Atostek ID Web Signer Proxy, which directs requests to the appropriate Atostek ID instance's SCS interface for each user. By default, this setting is *"false"*. When AVD support is enabled, the setting must be *"true"*. The organization's IT department typically sets this during installation, and users do not need to change it. Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect if the file is modified after installation.

4.5.23. Settings file parameter


ALLOWED BROWSERLESS AND FORWARD DOMAINS

You may use the setting parameter *"ALLOWED BROWSERLESS AND FORWARD DOMAINS"* directly in the application's settings file (*"C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\AtostekID.ini"*). The *"ALLOWED BROWSERLESS AND FORWARD DOMAINS"* parameter is used with the *erasmartcard.ehoito.fi* interface when performing browserless login, browserless signing, or */ForwardMessage* requests to destinations other than Atostek ERA or Edemo systems. The systems *era.ehoito.fi* and *edemo.atostek.com* are automatically allowed external addresses for these requests. If you want to add additional allowed addresses for production or testing purposes, specify the allowed addresses in the parameter, e.g., *"AllowedBrowserlessAndForwardDomains=era.ehoito.fi, edemo.atostek.com, edemo5.atostek.com"*. Please note that the settings file must be saved, and Atostek ID must be restarted after changes for the settings to take effect.


4.6. Updating

You can update Atostek ID by selecting *"Update"* from the application menu. Atostek ID first checks for updates and then displays the update status (Figures 9 and 10). If there are updates and you want to update the application to the latest version, select *"Yes"* in the window shown in Figure 10. The application will download and install the latest version (Figures 11 and 12).

Note! Updating the application requires administrator privileges, which are requested from the user automatically.



Figures 9 and 10. Status of updates when updates are not available and when updates are found.



Figures 11 and 12. Downloading and installing updates.

4.7. Signing documents via the application

In addition to Adobe Acrobat and PDF-XChange applications, PDF and PDF/A documents can also be signed directly via the Atostek ID application. The signature is compliant with the PAdES standard. The signature level (B-B, B-T, B-LT, B-LTA) is the highest possible the application can produce. This depends, for example, on whether the application has been configured with a timestamp service address via settings. In addition to the PAdES standard, the application also supports CAdES (B-B), JAdES (B-B), XAdES (B-B), and ASiC-E (B-B, B-T, B-LT) signature formats (detached signatures) for other document types.

To create a signature, open *"Sign Document"* from the application menu. Then, in the window that appears (see Figure 13), select the signature type and browse your computer to find the document to be signed.




Figure 13. PDF document signing in the Atostek ID application.

When the signing process begins, the user is first prompted to select the certificate to be used for the signature. Once the certificate is chosen, the user is asked for the corresponding PIN code. After entering the code, the card performs the signing, and the signature is attached to a copy of the original document, with the text “_signed” added to the end of the file name. The application will then inform whether the signing was successful or not.

4.8. Email encryption and signing (Outlook)

Emails can be encrypted and signed in Outlook using the certificates from the certificate card. In this case, Windows utilizes the Atostek ID Minidriver module, which is automatically installed with the Windows version of Atostek ID. More information about the Atostek ID Minidriver module can be found in the Atostek ID software integration guide. If necessary, please refer to Outlook's own documentation on email encryption and signing.

The certificate card can be activated in the Outlook application through the settings. Select “File” and then “Options”. In the window that opens, choose “Trust Center” and then “Trust Center Settings...”. Next, in the window that appears, select “Email Security” and add the certificates from your card through the settings. After this, you can use your card for email encryption and signing. To send an encrypted email to another person, you need to have the recipient's public key attached to their contact information.

4.9. Workstation login

You can authenticate to a Windows workstation using the authentication certificate from the certificate card. In this case, the Atostek ID Minidriver module is utilized; this module is automatically installed with the Windows version of Atostek ID. More information about the Atostek ID Minidriver module can be found in the Atostek ID software integration guide.

Once the driver is installed, the card reader is connected to the computer, the card is in the card reader, and the user's card information is paired with the user's AD account, the user can log into their workstation using the certificate card. In the Windows login screen, there should be an option for the certificate card displayed as a rectangular icon showing the card's contact surface (see Figure 14). When logging in, the PIN1 code of the card must be entered.




Figure 14. Workstation login view when the card is in the reader. The certificate card is displayed as a login option.

The Atostek ID software suite also offers a separate AD registration service for the organization's administration for AD pairing. The Atostek ID Minidriver can be configured to connect to this registration service initiated by the organization's administration, allowing the registration service to pair the card's information with the corresponding AD user. The registration service has its own installation package and instructions.

4.10. MIFARE Chip Management

When you have selected the MIFARE option during installation or through settings, the Atostek ID application menu will display an option "Mifare" (Figure 1). Selecting this opens the MIFARE chip sector management view, as shown in Figure 15.




Figure 15. MIFARE chip management view.

To read and write to the MIFARE chip, you need an NFC reader. Connect the reader to the computer, place the card in the reader, and enter the card's PIN1 when prompted to establish a secure connection. After that, press the "Connect to the card" button in the Mifare view. The view will indicate whether the connection is successful or not. The sixteen sectors of the MIFARE chip and the contents of their four blocks are automatically displayed in the view.

It is also possible to write to the chip's blocks in this view. **Please do not write anything to the MIFARE chip unless you are absolutely sure of what you are writing, and that writing is necessary! Writing is not required in normal use cases or for the application to function correctly. If needed, contact your organization's IT support.** Incorrect writing can lead to permanent locking of a sector (especially if writing occurs to the last block of a sector). Before writing, please review NXP's MIFARE Classic EV1 documentation. One relatively safe way to test writing is to write all bytes in sector 2, block 1 to 0xFF (i.e., input FF FF FF FF FF FF FF FF FF FF FF FF FF FF FF FF). Values can be restored by writing all bytes back to their original values (usually input 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00).

4.11. Logging

Atostek ID logs messages about the application's operation and error situations in its own log file. By default, the log file can be found at the path "*C:\Users\<user>\AppData\Local\Atostek Oy\Atostek ID\Error.log*." The log file can be opened by selecting "*Diagnostics*" from the menu and then "*Show Atostek ID log*" in the window that appears. The location of the log file can be changed through the settings.

By default, logging captures informational, warning, and error-level messages. You can enable debug-level logging through the settings, which provides more detailed logging and generates more log entries. Debug-level logging is particularly essential for troubleshooting error situations. You can also disable logging completely through the settings. In this case, the previous log file will not be deleted, but no new log messages will be recorded.

Atostek ID also logs error-level messages to the operating system's log (Microsoft Event Log).

4.12. Error reporting

In the application menu, you can find the option "*Error report*", which you can use to send an error report to Atostek's AIDERA service. However, a bug report itself is not a support request. If you encounter a problem, always contact your technical support first. If necessary, you will be asked to send an error report through this functionality. Only a limited number of error reports may be sent per day.

An error report is created by providing sufficient contact information and writing a description of the error (Figure 16). If the reader and the card are connected, the card information is filled in automatically.

Atostek ID - Error Report

NOTE! The Atostek ID error report is not a support request.
In case of problems, always contact your technical support first!

PDF

Basic information

First name*:
Mr. Test

Last name*:
Person

Registration number*:
12345678901

Email:

Error description*:
An example of an error description

Diagnostics info:
OK

☒ Run card tests

Send error report

Atostek ID - Send Error Report

Performing login test..... ✓

Performing sign test..... ✓

Sending error report..... ✓

Save PDF

OK

Figures 16 and 17. Error report and sending it.

Mandatory fields are in bold and marked with an asterisk. You can send an error report by clicking the "Send error report" button on the bottom right. Please note that the button cannot be pressed if any of the mandatory fields are missing.

If you wish, you can also save a PDF file from the error report to your computer using the "PDF" button on the top right. With the check box "Run card tests" at the bottom, you can choose whether to run card tests when sending an error report.

After sending the error report, a window opens where you can monitor sending progress (Figure 17). The window for sending an error report shows the status of the card tests only if you have selected the card tests to be run in the window in Figure 16. If the error report is sent successfully, the error report window (Figure 16) closes automatically. From the error report sending window (Figure 17), you can also save the error report as a PDF file by clicking the "Save PDF" button.

4.13. Diagnostics

You can open the diagnostics view of Atostek ID (Figure 18) from the application menu with "*Diagnostics*". When the view opens, tests are run, which takes a few seconds. The test results contain information about, among other things, the version of the Atostek ID application, connected readers and supported browsers.




Figure 18. Diagnostics view.

In the diagnostics view, you can also test login (authentication) and signing when the card is connected. You can select the hashing algorithm to be used using the radio buttons. The results of the login and signature test are saved in the "*Diagnostics report*" view.

You can view the error log of the Atostek ID application by clicking the *"Show Atostek ID log"* button. The error log opens in a separate window.

From the button *"Open Atostek ID test site"* you can test whether the Atostek ID application's erasmartcard.ehoito.fi interface works correctly. If the button does not open a white website with the text *"Test page loaded OK"*, something is wrong. For example, if the certificates required by the Atostek ID application are not set to trusted, the test page will not open correctly.

5. Frequently asked questions and error situations

Atostek ID displays separate error windows when error situations occur. These include scenarios where:

- Atostek ID cannot start the HTTPS server for the SCS interface on port 53952 because the port is not available.
- The operation cannot be performed because the card is not in the reader.
- The operation fails (for example, authentication or signing) due to invalid requests or card issues.

In addition, Atostek ID logs messages related to error situations and indicates with its logo if something is wrong.

5.1. Frequently asked questions

Q: The application shows a warning “Starting the SCS Server in port 53952 failed!” or “Starting the SCS CA Server in port 53953 failed!”.

A: This error typically occurs when the specified ports are not available, meaning another program is occupying them. Ensure that you do not have another card reader software installed or running that reserves these ports. These warnings only prevent the use of the application’s SCS interface and do not necessarily block other functionalities in your use cases. If closing and removing the other card reader software does not help, you can check via the command prompt which program is using the ports Atostek ID requires (using the netstat command). If possible, contact your organization’s IT support.

Q: Reading the card's information is not successful.

A: Is the card in the reader the right side up? Please note that the card's contact surface (the metallic square) must connect with the reader's contact surfaces for a connection to be established (readers other than NFC). You can also try gently wiping the contact surface, as any dirt can make reading difficult. Is the card reader properly connected to the device? Can you try another USB port? The card reader should be visible in addition to the application's views in Windows Device Manager (under Smart card readers). Is the card reader's own driver installed and up to date given that the card reader vendor provides a driver? Driver packages from card reader manufacturers are typically pre-installed with the operating system. However, they may also be missing or require an update. Driver packages can usually be downloaded from the card reader manufacturer's website.

Q: The application says that the PIN code is locked.

A: This means the PIN code has been entered incorrectly too many times in a row. You can unlock the PIN code using the PUK code, also known as the activation code number, through the application menu.

Q: What is the PUK code?

A: The PUK code, or activation code number, is the code that was sent to you in a separate letter when you ordered your card. The activation code number is used to activate the card and unlock locked PIN1 and PIN2 codes.

Q: Authentication or signing in the browser fails.

A: The specifics of this issue depend on which interface is being used. If mTLS authentication is involved (e.g., suomi.fi), please check through Device Manager that the Atostek ID Minidriver is installed for your smart card. This will be visible under “*Smart cards*” in Device Manager. If the Atostek ID driver is not visible or another driver appears, try removing the previous driver and reinstalling Atostek ID. If the issue is authentication or signing via the SCS or erasmartcard.ehoito.fi interface, you can check if you can access the interface's test page (<https://localhost:53952/> or <https://erasmartcard.ehoito.fi:44304/>). The browser usually indicates if access is denied due to DNS issues or untrusted certificates. For DNS issues, please contact your organization's IT department. Certificates can be manually installed as trusted in the browser or operating system's certificate store. You can also check the application's “*About*” view to see if the default ports required by the interfaces are in use by the application.

5.2. Other problem situations

5.2.1. Atostek ID and Minidriver

The Atostek ID Minidriver module is used in, for example, mTLS authentication (suomi.fi), signing documents with Adobe and PDF-XChange software, email encryption and signing with Outlook, and logging into a workstation with a certificate card. The module is automatically installed during system installation. However, issues may arise during installation or with the module. If you encounter issues, please check the following sections.

With older versions of Atostek ID, the required module packages are not installed automatically on the system. Sometimes, the required libraries (DLL files) may already be present on the machine. However, these files may be missing from the system in some cases. Missing files can be manually installed from [Microsoft's website](#) (vc_redist.x64.exe -> missing DLLs msvcp140.dll and vcruntime140.dll). **Starting from Atostek ID 4.3**, the packages are automatically included in the software installation, and do not need to be installed separately.

You can verify the module's installation by opening Device Manager when the card is in the reader. The card should appear under the Smart cards section, and the Atostek ID driver should be visible for the card, as shown in Figure 19. If no driver appears for the card, try reinstalling Atostek ID. If another driver is shown for the card, try removing it and then reinstalling Atostek ID.




Figure 19. Atostek ID Minidriver module installed correctly for the certificate card in the reader.

Once the driver is installed, you can check if it loads the card's certificates into the Windows certificate store (Figure 20). Open certmgr ("Manage user certificates") on your machine and navigate to the Personal/Certificates store. When the module is installed and the card is in the reader, the card's certificates should appear in the store. If the certificates do not appear, try removing the card from the reader and reinserting it. You can refresh the certificate store view by right-clicking the window and selecting "Refresh". If the card's certificates are already in the store, you can try removing them from the store and reinserting the card, which should make the certificates appear again and ensure they are up-to-date in the store.

For the successful operation of many use cases, it is important that the issuing certificate authorities (CA) for card certificates are set as trusted in the system certificate store. You can view the issuer certificate of your card by opening the "Readers and cards" view in the Atostek ID application and inspecting the card's certificate chain. Ensure that the CA certificate indicated for your card is listed as trusted in the Windows certificate store ("Manage computer certificates", "Trusted Root Certification Authorities", "Certificates"). During the installation of the Atostek ID application, DVV production issuers are added as trusted authorities. When using test cards, the user must manually add their test issuer as trusted.




Figure 20. User certificates visible in the certificate store.

Additionally, you can test functionality using the command prompt with the command `"certutil -scinfo"`. The command will ask for the PIN1, PIN2, PIN1 again, and PIN2 again. After entering the codes correctly, a window should open showing your certificate details. The command will print additional information in the command prompt if it fails.

If all the previous steps work and your use case still fails in the browser, try clearing the browser cache or using an incognito window to ensure that cached data does not interfere with the card's usage.